

# Kofax Copitrak Edge

## Kiosk Mode Configuration Guide

Version: 2.5.0

Date: 2019-09-25

The logo for KOFAX, consisting of the word "KOFAX" in a bold, blue, sans-serif font.

© 2019 Kofax. All rights reserved. Kofax is a trademark of Kofax, Inc., registered in the U.S. and/or other countries. All other trademarks are the property of their respective owners. No part of this publication may be reproduced, stored, or transmitted in any form without the prior written permission of Kofax.

# Introduction

Kiosk Mode is a special mode in which the Kofax Copitrak Edge application replaces the standard Windows shell and runs full screen. Kiosk Mode is a per user setting, so some users might be configured for Kiosk Mode while other users are not configured.

This is the standard configuration on the Kofax Edge hardware. In addition, the Kiosk Mode user on the Kofax Edge terminal is configured without a password and is set to log in automatically when the machine starts.

**Note:** The Copitrak Edge application is optimized to run with a resolution of 1024x768 scaled to 125%.

## Configuration

Since Kiosk Mode is a per user configuration, perform the configuration while logged in as the user who will be using Kiosk Mode.

### Enable Task Manager

If Task Manager is disabled, you must enable it to run the registry editor for the Kiosk Mode configuration on the Kofax Edge hardware.

1. Log in as administrator (**admin** on Kofax Edge).
2. Run the Local Group Policy Editor (`gpedit.msc`).
3. Go to **User Configuration > Administrative Templates > System > Ctrl+Alt+Del Options**.
4. Double-click **Remove Task Manager** and set it to **Disabled**.

### Configure Kiosk Mode

1. Log in as the user targeted for Kiosk Mode (**Edge** on Kofax Edge).
2. Click **Ctrl+Alt+Del** and select **Task Manager**.
3. Select **File > Run new task** from the menu and run `regedit`.
4. Go to `HKEY_Current_User\Software\Microsoft\Windows NT\CurrentVersion\Winlogon`.
5. Change the value of the Shell key to based on the Edge installation location. For example, `C:\Program Files (x86)\Kofax\Copitrak Edge Software\CopitrakEdge.exe`
6. Reboot.

**Note:** Once configuration is complete, consider disabling Task Manager by setting it back to **Enabled** to prevent users from accessing system options. Users can still run any location application using File or Run.

### Copitrak Edge Updater Service

Before you can update Edge in Kiosk Mode, make sure that you do not have any File Explorer windows opened. The Edge Updater Service will not work correctly with opened File Explorer windows or any other windows. If you need to open any window, please log in again as the Edge user after doing so.

If you have used Task Manager to configure Kiosk Mode as shown in the previous steps, then reboot before using Copitrak Edge. Once you log back in as the Edge user, Copitrak Edge is automatically logged in.