




Tungsten ReadSoft Invoices Tungsten License Server Installation and Configuration Guide

Version: 2025.1

Date: 2024-12-16

TUNGSTEN
AUTOMATION

© 2024 Tungsten Automation. All rights reserved.

Tungsten and Tungsten Automation are trademarks of Tungsten Automation Corporation, registered in the U.S. and/or other countries. All other trademarks are the property of their respective owners. No part of this publication may be reproduced, stored, or transmitted in any form without the prior written permission of Tungsten Automation.

Table of Contents

Preface.....	4
Related documentation.....	4
Getting help with Tungsten Automation products.....	4
Chapter 1: Introduction.....	6
Chapter 2: Get the license.....	7
Chapter 3: Installation and configuration.....	8
Install the Tungsten License Server on the server machine.....	8
Silent installation.....	8
Standard installation.....	9
Install the ReadSoft Invoices application on the client machine.....	9
Connect to the Tungsten License Server from the client machine.....	10
Activate your licenses.....	10
Automatically activate the licenses.....	10
Manually activate the licenses.....	11

Preface

This guide includes instructions to install, setup, configure, and use Tungsten License Server with ReadSoft Invoices 2025.1 or later for licensing.

Related documentation

For other online documentation related to Tungsten ReadSoft Invoices, refer to the [Tungsten ReadSoft Invoices Documentation](#) page.

You can also access the ReadSoft Invoices documentation in offline mode by downloading it from the [Tungsten Automation Electronic Fulfillment Site](#).

For a full documentation set, and how to access the documentation in offline mode, refer to the *Tungsten ReadSoft Invoices 2025.1 Release Notes*.

Getting help with Tungsten Automation products

The [Tungsten Automation Knowledge Portal](#) repository contains articles that are updated on a regular basis to keep you informed about the Tungsten Automation products. We encourage you to use the Knowledge Portal to obtain answers to your product questions.

To access the knowledge portal, go to [Tungsten Automation Knowledge Portal](#).

 The **Tungsten Automation Knowledge Portal** is optimized for use with Google Chrome, Mozilla Firefox, or Microsoft Edge.

The **Tungsten Automation Knowledge Portal** provides:

- Powerful search capabilities to help you quickly locate the information you need.
Type your search terms or phrase into the **Search** box, and then click the search icon.
- Product information, configuration details and documentation, including release news.
To locate articles, go to the Knowledge Portal home page and select the applicable Solution Family for your product, or click the **View All Products** button.

From the Knowledge Portal home page, you can:

- Access the Tungsten Automation Community (for all customers).
On the **Resources** menu, click the **Community** link.
- Access the Tungsten Automation Customer Portal (for eligible customers).
Go to the [Support Portal Information](#) page and click **Log in to the Customer Portal**.

- Access the Tungsten Automation Partner Portal (for eligible partners).
Go to the [Support Portal Information](#) page and click **Log in to the Partner Portal**.
- Access Tungsten Automation support commitments, lifecycle policies, electronic fulfillment details, and self-service tools.
Go to the [Support Details](#) page and select the appropriate article.

Chapter 1

Introduction

Tungsten ReadSoft Invoices 2025.1 use Tungsten License Server as its license-type. To migrate to Tungsten ReadSoft Invoices 2025.1 from previous ReadSoft Invoices versions that use other license types, you must first upgrade to Tungsten License Server.

 When installing or migrating to ReadSoft Invoices 2025.1 or later, a dialog box appears that informs you that if your license is not upgraded to Tungsten License Server, the application will stop working. You must click OK to confirm that you have the most recent Tungsten License Server. The dialog box appears for both the silent and manual installations. If you do not want the dialog box to appear during the installation, set the command-line parameter "SUPPRESSLICENSEWARN" flag value to 1 when installing ReadSoft Invoices using the "Tungsten ReadSoft Invoices 2025.1 Installation.exe" available in the \INVOICES installation folder. For more information, refer to the "Command-line installation" chapter in the *Tungsten ReadSoft Invoices Installation Guide*.

Chapter 2

Get the license

To get the new Tungsten License, email Tungsten Automation at contracts@tungstenautomation.com.

You will receive an email with the new license including the serial number and product code required for license activation.

 ReadSoft Invoices 2025.1 only support the Tungsten License Server.

Chapter 3

Installation and configuration

This chapter describes installing and configuring the Tungsten License Server to use ReadSoft Invoices 2025.1.

Do the following:

1. [Install the Tungsten License Server on the server machine](#)
2. [Install the ReadSoft Invoices application on the client machine](#)
3. [Connect to the Tungsten License Server from the client machine](#)
4. [Activate the licenses](#)



- In the distributed environments, the user must provide the UNC (shared path), for the GlobalPath folder during the installation; otherwise, licensing will not work.
- The GlobalPath folder contains a license configuration file called SALConfig.xml that stores the license server information used by all other client machines.
- The Invoices installer stores the GlobalPath in the following registry path, which the Tungsten license client SDK uses to communicate with the server:

"SharedLicenseServerFileUnc" registry key under "Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\Kofax\SALicClient".

DO NOT modify the above registry path unless recommended by Tungsten Automation.

Install the Tungsten License Server on the server machine

To connect to the Tungsten License Server from the client machine, install the Tungsten License Server on the server machine.

You can use either of the following ways:

- [Silent installation](#)
- [Standard installation](#)

Silent installation

To perform the silent installation, do the following.

1. From your ReadSoft Invoices installation files, go to \License Server and copy the KofaxLicenseServer-6.6.1.bat file path. For example, "C:

```
\Program Files\TungstenReadSoftInvoices-2025.1\License Server  
\KofaxLicenseServer-6.6.1.bat".
```

2. On the **Start** menu, go to **All apps > Command Prompt**, right-click and select **Run as administrator**.
The **Command Prompt** window appears.
3. Paste the copied file path in quotation marks (" ") and press **Enter**.
The installation starts.
4. To confirm that the installation is complete, on the Windows **Start** menu, go to **All apps > Control Panel > Programs > Programs and Features** and look for the **Tungsten License Server**.
The **Tungsten License Server** will be visible.
5. Close the **Command Prompt** window.

Standard installation

To perform the standard installation, do the following.

1. From your ReadSoft Invoices installation files, go to `\License Server` and run `KofaxLicenseServer-6.6.1.msi`.
The **Tungsten License Server** setup dialog box appears.
2. Click **Next**.
The **Customer Information** dialog box appears.
3. Enter the username and organization name or click **Next** to accept the default values.
The **Destination Folder** dialog box appears.
4. The folder (`C:\Program Files (x86)\Kofax \License Server\`) is selected by default.
Click **Change** to select a different folder.
5. Click **Next**.
The **Ready to Install the Program** dialog box appears.
6. Click **Install**.
The installation begins.
7. After installation, click **Finish** to close the window.
8. Note the server machine hostname or IP address. You will need it to connect to the License Server from the client machine.

 You can install a second License Server on a different machine and use it as a backup server for ReadSoft Invoices. Follow the same steps given above.

Install the ReadSoft Invoices application on the client machine

To connect to the Tungsten License Server from the client machine, you must first install the ReadSoft Invoices application on the client machine, and then connect to the Tungsten License Server.

1. From your ReadSoft Invoices installation files, go to `\INVOICES`.

2. Run `Tungsten ReadSoft Invoices 2025.1 Installation.exe` and select appropriate options. Refer to the *ReadSoft Invoices Installation Guide* for more information.

Connect to the Tungsten License Server from the client machine

1. On your machine, go to the **Start** menu.
2. Click **All apps > ReadSoft > Tungsten License Utility**.
The **Tungsten License Utility** window appears.
3. Click **File > Select Servers**.
The **Select Servers** dialog box appears.
4. In the **Primary License Server** box, enter the license server name or IP address of the primary license server that you noted earlier (see [Install the Tungsten License Server on the server machine](#)). If you have installed a secondary license server, enter the server name or IP address in the **Backup License Server** box.
5. Click **OK**.
You are connected to the license server.

Activate your licenses

You can activate your licenses in one of the following ways:

- [Automatically activate the licenses](#)
- [Manually activate the licenses](#)

 You need to activate the Tungsten License Server only once from a single client machine, not all.

Automatically activate the licenses

Use the Tungsten License Utility on the client machine to activate the licenses automatically. The automatic activation method requires an internet connection.

1. On the **Start** menu, click **All apps > ReadSoft > Tungsten License Utility**.
The **Tungsten License Utility** window appears.
2. Select **File > Activate**.
The **Activate** dialog box appears.
3. Enter the serial number in the **Serial number** box, and the product number in the **Product code** box.

 The serial number and product code are issued to you when you purchase the product.

4. Click **Automatic**.

The Tungsten License Server initiates automatic activation and upon completion, the utility displays all the license features.

 If automatic activation is not successful from the installer or license utility, use the [Tungsten Automation support for manual activation](#).

Manually activate the licenses

Manually activate licenses only if they cannot be activated automatically. Manual activation requires an activation code that you can get from Tungsten Automation. To get the activation code, send your Machine ID to Tungsten Automation. The Machine ID is also required to move licenses from one server to another. Alternatively, visit the product license activation support if you have the serial number and product code.

 Make sure the activation code is not altered.

Get the activation code

1. Go to the **Start** menu.
2. Click **All apps > ReadSoft > Tungsten License Utility**.
The **Tungsten License Utility** window appears.
3. Select **File > Activate**.
The **Activate** dialog box appears.
4. Note down the value in the **Machine ID** box.
The **Manual Activation** dialog box appears.
5. Email the Machine ID to Tungsten Automation at contracts@tungstenautomation.com to receive an activation code.
Once you receive the activation code, you can activate the license.

Activate the license

1. Go to the **Start** menu.
2. Click **All apps > ReadSoft > Tungsten License Utility**.
The **Tungsten License Utility** window appears.
3. Select **File > Activate**.
The **Activate** dialog box appears.
4. Click **Manual**.
The **Manual Activation** dialog box appears.
5. Enter the activation code that you received from Tungsten Automation in the **Paste activation code below** box.
The Tungsten license server initiates the manual activation. After successful activation, the utility displays all the license features.